

August 12, 2023

#### **Process for Establishing a New Lawn**

Establishing a new lawn at a home or business construction site or redoing an existing lawn that is mostly weeds, involves soil tillage and destruction of existing grass. The timing of mid-August to late September is the same as renovating a lawn. This time period provides less weed competition compared to the spring and favorable temperature and moisture conditions. Tips for establishing a lawn are provided.

For this area, turf-type tall fescue is the best grass for lawns. It has few insect and disease problems, competes well with most weeds, has good traffic tolerance, establishes relatively easily, has a widespread fertility range, tolerates full sun, adapts to wet and droughty soils or clay and sandy soils, and is recommended for areas with shade. A fine fescue can be used in the shade if the turf-type fescue will not grow there; however, the leaf texture and plant habit are different from the turf-type fescue. It is difficult for turfgrass to grow in heavy shade.

Although tall fescue is normally a bunchgrass, when sown at the proper rate of 6 pounds per 1000 square feet, leaf coarseness or clumping is not a problem.

Any turf-type fescue is preferred. KY-31 is better suited for very low-maintenance sites or utility turf areas.

Mixtures of tall fescue with other types of grass are not recommended because coarse and fine textures mixed together make differences in blade widths noticeable. Under optimum conditions, the germination time for tall fescue is 7-10 days. However, it may take longer when moisture is lacking, when the surface soil temperature remains cold, or even when there are periods of wet/dry conditions. Germination also takes longer when old or poor quality seed is used or when new seed harvested in the summer is used for a late summer seeding. This seed may have a short-term dormancy factor that slows down germination for several weeks.

Proper soil preparation is key to the success of establishing a fescue lawn. It is easier to amend the soil before the lawn is established. Rember to call 811 before tilling the soil to mark utility lines.

An advantage to tilling the soil is the ability to improve it by incorporating organic matter. Adding organic matter to the existing topsoil is the best way to improve it. Peat moss, well-decomposed sawdust, well-rotted and weed-free manure, and compost will improve soil that is too sandy, contains too much clay, or is compacted. Use 2 to 3 cubic yards of organic matter for every 1000 square feet of lawn. Spread it evenly over the surface and roto-till or disk it into the upper 6 inches of soil before seeding. Organic matter helps to improve water drainage and reduce compaction in clay soils. Do not work the soil when it is wet because the soil will compact more, thus losing the benefits of the organic matter.

Before planting the seed, it is best to test the soil to determine the need for lime or fertilizer. Soil can be tested through your county Cooperative Extension Service Office.

Generally, the tests are completed in 10 to 14 days. Testing the soil may save money and prevent problems in the future when certain nutrient or pH levels become too high. After applying the recommended amount of fertilizer and lime, work it into the top 4 to 6 inches of soil before seeding.

Next, allow the soil to settle in the newly worked area through two or three good rains or irrigations. If the water puddles, drain or fill in these low spots. Good surface drainage is a must! The final seedbed should be firm but not compacted and free of large clods and rocks.

Seeding the lawn can be accomplished with a rotary seeder or drop-type seeder and fertilizer spreader. Seeding rate for tall fescue is 6 pounds per 1000 square feet. For uniform distribution of the seed, divide the seed into two equal lots with the second lot seeded at right angles to the first. The seed should be covered by raking over it lightly or rolling but avoid making a smooth surface.

The seeded area is covered with mulch such as straw that is as weed free as possible or other suitable material. The mulch should be spread thin enough to expose about 50 percent of the soil surface. It takes approximately one bale of straw per 1000 square feet of area. Water the newly seeded area frequently, especially if you do not use mulch. Keep the soil surface moist until the grass seedlings become established.

After the tall fescue grass seedlings begin to grow, mow at the recommended height of 2.5 to 3 inches. Sharpen the mower blade so the grass leaf blade is cut cleanly and not torn. By

mowing early and not letting excessive grass accumulate, the texture will be finer, many upright weeds will be killed, and the turf will become dense.

For more information about establishing a new lawn, contact the Daviess County Cooperative Extension Service at 270-685-8480 or email at <a href="mailto:Annette.heisdorffer@uky.edu">Annette.heisdorffer@uky.edu</a>.

### **Annette's Tip:**

When purchasing seed, look for the words Certified seed in a block on the bag or on a tag attached to the bag. Certified seed guarantees that what the tag states is in the bag. Typically, Certified seed contains few weed seeds and includes this information on the tag. More information is available in the publication "Lawn Establishment in KY" (http://www2.ca.uky.edu/agcomm/pubs/AGR/AGR50/AGR50.pdf).

The Martin-Gatton College of Agriculture, Food and Environment is an Equal Opportunity Organization with respect to education and employment and authorization to provide research, education information and other services only to individuals and institutions that function without regard to economic or social status and will not discriminate on the basis of race, color, ethnic origin, national origin, creed, religion, political belief, sex, sexual orientation, gender identity, gender expression, pregnancy, marital status, genetic information, age, veteran status, physical or mental disability or reprisal or retaliation for prior civil rights activity.